

---

# I'm ready to connect to Q-Link.

---

## CONNECT WITH A REAL 64/128:

### PC SIDE SOFTWARE:

Software required: TCPSER4j-rc6.0  
Requires JAVA  
Use the config file from  
www.quantum-link.org.  
(Unzip and copy file to TCPSER4j folder)

### ALTERNATIVE PC SOFTWARE:

You can also use: TCPSER  
Use the follow line to start the PC side.  
tcpser -d /dev/ttyS0 -s 1200 -i "e0&k0&c0"  
-n "5551212=server:port -ts5

### COMMODORE SIDE SOFTWARE:

Software required: Quantumlink.d64  
Convert this .d64 to a real disk,  
and use the following settings:  
Modem: Hayes or Hayes-compatible  
Speed: 1200 Baud  
Dial: Automatic  
Phone: Tone  
Number: +5551212

## CONNECT WITH VICE 1.15:

### PC SIDE SOFTWARE:

Software required: TCPSER4j-rc6.0 Requires JAVA  
Download the config.xml file from  
www.quantum-link.org and  
place in the TCPSER4j folder.

Use WinVICE-1.15 (version 1.16 will not work)  
Use the following line to start VICE after  
TCPSER4j is started:  
x64 -rsdev1 127.0.0.1:232 -rsuser 1200 -rsuserdev 0

### VICE SIDE SOFTWARE:

Software required: Quantumlink.d64  
Load this disk into VICE, and use the following settings:  
Modem: Other command driven modems  
Speed: 1200 Baud  
Dial: Automatic  
Phone: Tone  
Number: +5551212 Note: - & + are switched in vice.

### HOW TO CONNECT:

Qlink software will display:  
Type commands to modem, then  
press F1 when connection is made.  
Type ATDT1 and press ENTER  
When you see a CONNECT 38400 message, press F1

## CONNECT WITH VICE 1.16:

### PC SIDE SOFTWARE:

Software required: WinVICE 1.16  
Download the custom x64.exe file from  
www.quantum-link.org and replace the  
x64.exe file in the folder WinVICE was extracted.  
Make the following configuration entries:  
Settings --> RS232 Settings Change RS232 Device 1 to:  
66.135.38.238:5190

Settings --> Cart I/O Settings --> RS232 Userport settings  
Enable RS232 Userport, Userport Device RS232 Device 1  
Userport baud rate 1200

### VICE SIDE SOFTWARE:

Software required: Quantumlink.d64  
Load this disk into VICE, and use the following settings:  
Modem: Other command driven modems  
Speed: 1200 Baud, Dial: Automatic, Phone: Tone  
Number: +5551212 Note: - & + are switched in vice.

### HOW TO CONNECT:

Qlink software will display:  
Type commands to modem, then  
press F1 when connection is made. Press F1 and enjoy!

For faster service, visit  
[www.quantum-link.org](http://www.quantum-link.org)  
[info@quantum-link.org](mailto:info@quantum-link.org)

